

BED BUG SERVICE PROTOCOL



Introduction and Overview - Your attention to detail and thoroughness of service are key to eliminating bed bug infestations. Take your time, be thorough, work smart. Make sure that you have sufficient EcoRaider product on hand to complete the job. If necessary, a dust product can be used in conjunction with EcoRaider. A vacuum (with bag) is used to remove evidence of bed bugs or their eggs. When finished, remove the bag, apply EcoRaider into the bag, wrap and place it in a garbage bag and dispose in an outdoor trash receptacle.

Bed linens, comforters, etc. – Inspect, remove bugs with vacuum, remove linens and place in a 30-gal trash bag for heating in the clothes dryer.

Mattress - Inspect top surface and remove any visible "evidence" with the vacuum; treat folds, tufts and seams with EcoRaider; stand mattress against wall and repeat for bottom surface.

Box Springs - Inspect top surface and remove visible "evidence" with vacuum; treat folds, tufts and seams with EcoRaider; stand mattress against wall and vacuum bed bugs and/or eggs from bottom. Evaluate the condition of dust cover; with permission, remove the dust cover and treat the inner areas with EcoRaider.

Bed Frame, Headboard, Footboard - Vacuum bed frame and spray with EcoRaider. Fan spray back of the headboard and footboard. Crack and crevice headboard and footboard with dust where frame and bed rail meet. Fan spray along the inside of bed rails; pay close attention to cracks and screw holes in the bed rails.

Carpeted Areas - Pull the carpet from tack strip behind beds and upholstered furniture and about 4 feet from either side. Inspect and vacuum. Treat gap between baseboard and floor with dust. Fan spray the tack strip.

Electrical Outlets / Switch Covers - Remove outlet/switch plate covers; dust around the electrical box.

Hardwood Floors - Spray gaps (larger than 1/16") in floors under bed and upholstered furniture.

Furniture (wood) - Remove drawers, vacuum and spray corner edges, set aside. Inspect the interior, back and bottom of furniture, vacuum and fan spray.

Furniture upholstered - Inspect cushions, zipper seams, dust ruffles, folds on the arms, and any other area that could hide bed bugs. Vacuum evidence and spray EcoRaider to areas that persons will not directly contact when sitting. Turn item over - inspect, vacuum and fan spray bottom. Place a small hole in dust cover every three feet around the perimeter. Insert wand into holes and inject EcoRaider through each hole. Fan spray into the joints where sides, back, and bottom meet. Use your covered foot or your free hand to push seat away from sides or back and treat into the gap you have created. (Treat sleeper sofas like regular beds.)

Wall Hangings, Door/Window Frames, Perimeters - Remove wall hangings and inspect. Do not treat pictures or paintings. Document any pictures that are infested; let owner determine how to proceed with the pictures. Crack and crevice door and window frames with EcoRaider. Fan spray baseboards, wall/wall corner junctions and wall/ceiling junction.

Closets - Inspect, crack and crevice all available areas and fan spray any baseboard, wall/wall or wall/ceiling junction that is accessible.

Luggage / Suitcases - Inspect and treat seams, folds and edges; spray the entire surface with EcoRaider.

Other Areas (where bed bugs are not normally found) - If you find an infestation in an unsuspecting room, treat the furniture in the room using the protocol above as thoroughly as possible. Fan spray baseboards and wall/wall junctions in non-infested areas (i.e. dining room, bathrooms, unfinished basement, etc.)

Date: _____ Inspector: _____

Address: _____

Control Strategy



BEDBUG INSPECTION & TREATMENT REPORT

Check if applicable	LOCATION	Control Strategy			
		Inspect	Vacuum	Apply Dust	EcoRaider
Bedroom #1					
<input type="checkbox"/>	Bed linens, comforters, etc.	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Mattress(s)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Box Springs	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Frame, Headboard, Footboard	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Furniture (Wood)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Furniture (Upholstered)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Bedroom #2					
<input type="checkbox"/>	Bed linens, comforters, etc.	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Mattress(s)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Box Springs	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Frame, Headboard, Footboard	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Furniture (Wood)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Furniture (Upholstered)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Bedroom #3					
<input type="checkbox"/>	Bed linens, comforters, etc.	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Mattress(s)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Box Springs	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Frame, Headboard, Footboard	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Furniture (Wood)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Furniture (Upholstered)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Other Areas					
<input type="checkbox"/>	Carpeted Areas	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Hardwood Floor	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Electrical Outlet/Switch Cover	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Wall Hangings	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Door / Window Frames	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Perimeters	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Closets	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Luggage/Suitcases	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
<input type="checkbox"/>	Sofa / Other Furniture	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>